NAG Library Routine Document

G01HBF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of **bold italicised** terms and other implementation-dependent details.

1 Purpose

G01HBF returns the upper tail, lower tail or central probability associated with a multivariate Normal distribution of up to ten dimensions.

2 Specification

```
FUNCTION GO1HBF (TAIL, N, A, B, XMU, SIG, LDSIG, TOL, WK, LWK, IFAIL)

REAL (KIND=nag_wp) GO1HBF

INTEGER N, LDSIG, LWK, IFAIL

REAL (KIND=nag_wp) A(N), B(N), XMU(N), SIG(LDSIG,N), TOL, WK(LWK)

CHARACTER(1) TAIL
```

3 Description

Let the vector random variable $X = (X_1, X_2, \dots, X_n)^T$ follow an n-dimensional multivariate Normal distribution with mean vector μ and n by n variance-covariance matrix Σ , then the probability density function, $f(X : \mu, \Sigma)$, is given by

$$f(X:\mu,\Sigma) = (2\pi)^{-(1/2)n} |\Sigma|^{-1/2} \exp\left(-\frac{1}{2}(X-\mu)^{\mathsf{T}} \Sigma^{-1}(X-\mu)\right).$$

The lower tail probability is defined by:

$$P(X_1 \le b_1, \dots, X_n \le b_n : \mu, \Sigma) = \int_{-\infty}^{b_1} \dots \int_{-\infty}^{b_n} f(X : \mu, \Sigma) dX_n \dots dX_1.$$

The upper tail probability is defined by:

$$P(X_1 \ge a_1, \dots, X_n \ge a_n : \mu, \Sigma) = \int_{a_1}^{\infty} \dots \int_{a_n}^{\infty} f(X : \mu, \Sigma) dX_n \dots dX_1.$$

The central probability is defined by:

$$P(a_1 \leq X_1 \leq b_1, \dots, a_n \leq X_n \leq b_n : \mu, \Sigma) = \int_{a_1}^{b_1} \dots \int_{a_n}^{b_n} f(X : \mu, \Sigma) dX_n \dots dX_1.$$

To evaluate the probability for $n \geq 3$, the probability density function of X_1, X_2, \ldots, X_n is considered as the product of the conditional probability of $X_1, X_2, \ldots, X_{n-2}$ given X_{n-1} and X_n and the marginal bivariate Normal distribution of X_{n-1} and X_n . The bivariate Normal probability can be evaluated as described in G01HAF and numerical integration is then used over the remaining n-2 dimensions. In the case of n=3, D01AJF is used and for n>3 D01FCF is used.

To evaluate the probability for n = 1 a direct call to G01EAF is made and for n = 2 calls to G01HAF are made.

4 References

Kendall M G and Stuart A (1969) The Advanced Theory of Statistics (Volume 1) (3rd Edition) Griffin

Mark 24 G01HBF.1

5 Parameters

1: TAIL - CHARACTER(1)

Input

On entry: indicates which probability is to be returned.

TAIL = 'L'

The lower tail probability is returned.

TAIL = 'U'

The upper tail probability is returned.

TAIL = 'C'

The central probability is returned.

Constraint: TAIL = 'L', 'U' or 'C'.

2: N – INTEGER

Input

On entry: n, the number of dimensions.

Constraint: $1 \le N \le 10$.

3: A(N) - REAL (KIND=nag wp) array

Input

On entry: if TAIL = 'C' or 'U', the lower bounds, a_i , for i = 1, 2, ..., n.

If TAIL = 'L', A is not referenced.

4: $B(N) - REAL (KIND=nag_wp) array$

Input

On entry: if TAIL = 'C' or 'L', the upper bounds, b_i , for i = 1, 2, ..., n.

If TAIL = 'U' B, is not referenced.

Constraint: if TAIL = 'C', A(i) < B(i), for i = 1, 2, ..., n.

5: XMU(N) – REAL (KIND=nag wp) array

Input

On entry: μ , the mean vector of the multivariate Normal distribution.

6: SIG(LDSIG,N) – REAL (KIND=nag_wp) array

Input

On entry: Σ , the variance-covariance matrix of the multivariate Normal distribution. Only the lower triangle is referenced.

Constraint: Σ must be positive definite.

7: LDSIG – INTEGER

Input

On entry: the first dimension of the array SIG as declared in the (sub)program from which G01HBF is called.

Constraint: LDSIG \geq N.

8: TOL – REAL (KIND=nag wp)

Input

On entry: if n > 2 the relative accuracy required for the probability, and if the upper or the lower tail probability is requested then TOL is also used to determine the cut-off points, see Section 7.

If n = 1, TOL is not referenced.

Suggested value: TOL = 0.0001.

Constraint: if N > 1, TOL > 0.0.

G01HBF.2 Mark 24

```
9: WK(LWK) – REAL (KIND=nag_wp) array
10: LWK – INTEGER

Workspace
Input
```

On entry: the length of workspace provided in array WK. This workspace is used by the numerical integration routines D01AJF for n = 3 and D01FCF for n > 3.

If n = 3, then the maximum number of sub-intervals used by D01AJF is LWK/4. Note, however, increasing LWK above 1000 will not increase the maximum number of sub-intervals above 250.

If n > 3 the maximum number of integrand evaluations used by D01FCF is $\alpha(\text{LWK}/n - 1)$, where $\alpha = 2^{n-2} + 2(n-2)^2 + 2(n-2) + 1$.

If n = 1 or 2, then WK will not be used.

Suggested value: 2000 if n > 3 and 1000 if n = 3.

Constraints:

```
if N = 1, LWK \geq 1; if N \geq 3, LWK \geq 4 \times N.
```

11: IFAIL – INTEGER

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, because for this routine the values of the output parameters may be useful even if IFAIL $\neq 0$ on exit, the recommended value is -1. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Note: G01HBF may return useful information for one or more of the following detected errors or warnings.

Errors or warnings detected by the routine:

IFAIL = 3

If on exit IFAIL = 1, 2 or 3, then G01HBF returns zero.

```
\begin{split} \text{IFAIL} &= 1 \\ &\quad \text{On entry, N} < 1, \\ &\quad \text{or} \qquad \text{N} > 10, \\ &\quad \text{or} \qquad \text{LDSIG} < \text{N}, \\ &\quad \text{or} \qquad \text{TAIL} \neq \text{'L', 'U' or 'C',} \\ &\quad \text{or} \qquad \text{N} > 1 \text{ and TOL} \leq 0.0, \\ &\quad \text{or} \qquad \text{LWK is too small.} \end{split} \text{IFAIL} = 2 \text{On entry, TAIL} = \text{'C' and A}(i) \geq \text{B}(i), \text{ for some } i = 1, 2, \dots, n. \end{split}
```

On entry, Σ is not positive definite, i.e., is not a correct variance-covariance matrix.

Mark 24 G01HBF.3

G01HBF NAG Library Manual

IFAIL = 4

The requested accuracy has not been achieved, a larger value of TOL should be tried or the length of the workspace should be increased. The returned value will be an approximation to the required result.

```
IFAIL = 5
```

Round-off error prevents the requested accuracy from being achieved; a larger value of TOL should be tried. The returned value will be an approximation to the required result. This error will only occur if n = 3.

7 Accuracy

The accuracy should be as specified by TOL. When on exit IFAIL = 4 the approximate accuracy achieved is given in the error message. For the upper and lower tail probabilities the infinite limits are approximated by cut-off points for the n-2 dimensions over which the numerical integration takes place; these cut-off points are given by $\Phi^{-1}(\text{TOL}/(10 \times n))$, where Φ^{-1} is the inverse univariate Normal distribution function.

8 Further Comments

The time taken is related to the number of dimensions, the range over which the integration takes place $(b_i - a_i)$, for i = 1, 2, ..., n and the value of Σ as well as the accuracy required. As the numerical integration does not take place over the last two dimensions speed may be improved by arranging X so that the largest ranges of integration are for X_{n-1} and X_n .

9 Example

This example reads in the mean and covariance matrix for a multivariate Normal distribution and computes and prints the associated central probability.

9.1 Program Text

```
Program g01hbfe
     GO1HBF Example Program Text
1
     Mark 24 Release. NAG Copyright 2012.
      .. Use Statements ..
     Use nag_library, Only: g01hbf, nag_wp
!
      .. Implicit None Statement ..
     Implicit None
      .. Parameters ..
!
     Integer, Parameter
                                        :: nin = 5, nout = 6
!
      .. Local Scalars ..
     Real (Kind=nag_wp)
                                        :: prob, tol
     Integer
                                        :: i, ifail, ldsig, lwk, n
                                        :: tail
     Character (1)
!
      .. Local Arrays ..
     Real (Kind=nag_wp), Allocatable :: a(:), b(:), sig(:,:), wk(:), xmu(:)
      .. Intrinsic Procedures ..
!
     Intrinsic
                                        :: max
      .. Executable Statements ..
     Write (nout,*) 'GO1HBF Example Program Results'
     Write (nout,*)
     Skip heading in data file
     Read (nin,*)
     Read in the problem size
     Read (nin,*) n, tol, tail
     Use more workspace, unless N is very large
```

G01HBF.4 Mark 24

```
as LWK also defines the number of sub-intervals
      1wk = max(2000, 4*n)
      ldsig = n
      Allocate (a(n),b(n),xmu(n),sig(ldsig,n),wk(lwk))
     Read in the means
      Read (nin,*) xmu(1:n)
      Read in the variance covariance matrix
      Read (nin,*)(sig(i,1:n),i=1,n)
      Read in bounds
      If (tail=='C' .Or. tail=='C' .Or. tail=='U' .Or. tail=='u') Then
       Read (nin,*) a(1:n)
      End If
      If (tail=='C' .Or. tail=='c' .Or. tail=='L' .Or. tail=='l') Then Read (nin,*) b(1:n)
      End If
      Calculate probability
      ifail = -1
      \verb|prob| = g01hbf(tail,n,a,b,xmu,sig,ldsig,tol,wk,lwk,ifail)|
      If (ifail/=0) Then
        If (ifail<=3) Then
          Go To 100
        End If
      End If
      Display results
      Write (nout, 99999) 'Multivariate Normal probability =', prob
100
     Continue
99999 Format (1X,A,F7.4)
    End Program g01hbfe
```

9.2 Program Data

```
G01HBF Example Program Data
4 0.00001 'c'
0.0 0.0 0.0 0.0
1.0 0.9 0.9 0.9
0.9 1.0 0.9 0.9
0.9 0.9 1.0 0.9
0.9 0.9 0.9 1.0
-2.0 -2.0 -2.0 -2.0
2.0 2.0 2.0 2.0
```

9.3 Program Results

```
GO1HBF Example Program Results

Multivariate Normal probability = 0.9142
```

Mark 24 G01HBF.5 (last)