

NAG Library Routine Document

X04CAF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

X04CAF is an easy-to-use routine to print a real matrix stored in a two-dimensional array.

2 Specification

```
SUBROUTINE X04CAF (MATRIX, DIAG, M, N, A, LDA, TITLE, IFAIL)
```

```
INTEGER           M, N, LDA, IFAIL
REAL (KIND=nag_wp) A(LDA,*)
CHARACTER(*)      TITLE
CHARACTER(1)      MATRIX, DIAG
```

3 Description

X04CAF prints a real matrix. It is an easy-to-use driver for X04CBF. The routine uses default values for the format in which numbers are printed, for labelling the rows and columns, and for output record length.

X04CAF will choose a format code such that numbers will be printed with an F8.4, an F11.4 or a 1PE13.4 format. The F8.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 1.0. The F11.4 code is chosen if the sizes of all the matrix elements to be printed lie between 0.001 and 9999.9999. Otherwise the 1PE13.4 code is chosen.

The matrix is printed with integer row and column labels, and with a maximum record length of 80.

The matrix is output to the unit defined by X04ABF.

4 References

None.

5 Parameters

1: MATRIX – CHARACTER(1) *Input*

On entry: indicates the part of the matrix to be printed.

MATRIX = 'G'

The whole of the rectangular matrix.

MATRIX = 'L'

The lower triangle of the matrix, or the lower trapezium if the matrix has more rows than columns.

MATRIX = 'U'

The upper triangle of the matrix, or the upper trapezium if the matrix has more columns than rows.

Constraint: MATRIX = 'G', 'L' or 'U'.

- 2: DIAG – CHARACTER(1) *Input*
On entry: unless MATRIX = 'G', DIAG must specify whether the diagonal elements of the matrix are to be printed.
 DIAG = 'B'
 The diagonal elements of the matrix are not referenced and not printed.
 DIAG = 'U'
 The diagonal elements of the matrix are not referenced, but are assumed all to be unity, and are printed as such.
 DIAG = 'N'
 The diagonal elements of the matrix are referenced and printed.
 If MATRIX = 'G', then DIAG need not be set.
Constraint: if MATRIX \neq 'G', DIAG = 'B', 'U' or 'N'.
- 3: M – INTEGER *Input*
 4: N – INTEGER *Input*
On entry: the number of rows and columns of the matrix, respectively, to be printed.
 If either M or N is less than 1, X04CAF will exit immediately after printing TITLE; no row or column labels are printed.
- 5: A(LDA,*) – REAL (KIND=nag_wp) array *Input*
Note: the second dimension of the array A must be at least $\max(1, N)$.
On entry: the matrix to be printed. Only the elements that will be referred to, as specified by parameters MATRIX and DIAG, need be set.
- 6: LDA – INTEGER *Input*
On entry: the first dimension of the array A as declared in the (sub)program from which X04CAF is called.
Constraint: $LDA \geq \max(1, M)$.
- 7: TITLE – CHARACTER(*) *Input*
On entry: a title to be printed above the matrix.
 If TITLE = ' ', no title (and no blank line) will be printed.
 If TITLE contains more than 80 characters, the contents of TITLE will be wrapped onto more than one line, with the break after 80 characters.
 Any trailing blank characters in TITLE are ignored.
- 8: IFAIL – INTEGER *Input/Output*
On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.
 For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. **When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.**
On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry `IFAIL = 0` or `-1`, explanatory error messages are output on the current error message unit (as defined by `X04AAF`).

Errors or warnings detected by the routine:

`IFAIL = 1`

On entry, `MATRIX` \neq 'G', 'L' or 'U'.

`IFAIL = 2`

On entry, `MATRIX = 'L'` or `'U'`, but `DIAG` \neq 'N', 'U' or 'B'.

`IFAIL = 3`

On entry, `LDA < M`.

7 Accuracy

Not applicable.

8 Further Comments

A call to `X04CAF` is equivalent to a call to `X04CBF` with the following argument values:

```
NCOLS = 80
INDENT = 0
LABROW = 'I'
LABCOL = 'I'
FORM = ' '
```

9 Example

This example program calls `X04CAF` twice, first to print a 3 by 5 rectangular matrix, and then to print a 5 by 5 lower triangular matrix.

9.1 Program Text

```
Program x04cafe

!      X04CAF Example Program Text

!      Mark 24 Release. NAG Copyright 2012.

!      .. Use Statements ..
Use nag_library, Only: nag_wp, x04caf
!      .. Implicit None Statement ..
Implicit None
!      .. Parameters ..
Integer, Parameter          :: nmax = 5, nout = 6
Integer, Parameter          :: lda = nmax
!      .. Local Scalars ..
Integer                      :: i, ifail, j
!      .. Local Arrays ..
Real (Kind=nag_wp)          :: a(lda,nmax)
!      .. Intrinsic Procedures ..
Intrinsic                    :: real
!      .. Executable Statements ..
Write (nout,*) 'X04CAF Example Program Results'

Write (nout,*)
Flush (nout)

!      Generate an array of data
```

```

      Do j = 1, nmax
        Do i = 1, lda
          a(i,j) = real(10*i+j,kind=nag_wp)
        End Do
      End Do

!      Print 3 by nmax rectangular matrix

      ifail = 0
      Call x04caf('General', ' ', 3, nmax, a, lda, 'Example 1:', ifail)

      Write (nout,*)
      Flush (nout)

!      Print nmax by nmax lower triangular matrix

      ifail = 0
      Call x04caf('Lower', 'Non-unit', nmax, nmax, a, lda, 'Example 2:', ifail)

      End Program x04cafe

```

9.2 Program Data

None.

9.3 Program Results

X04CAF Example Program Results

Example 1:

	1	2	3	4	5
1	11.0000	12.0000	13.0000	14.0000	15.0000
2	21.0000	22.0000	23.0000	24.0000	25.0000
3	31.0000	32.0000	33.0000	34.0000	35.0000

Example 2:

	1	2	3	4	5
1	11.0000				
2	21.0000	22.0000			
3	31.0000	32.0000	33.0000		
4	41.0000	42.0000	43.0000	44.0000	
5	51.0000	52.0000	53.0000	54.0000	55.0000
