NAG Library Routine Document

F04AMF

Note: before using this routine, please read the Users' Note for your implementation to check the interpretation of *bold italicised* terms and other implementation-dependent details.

1 Purpose

F04AMF calculates the accurate least squares solution of a set of m linear equations in n unknowns, $m \ge n$ and rank = n, with multiple right-hand sides, AX = B, using a QR factorization and iterative refinement.

2 Specification

```
SUBROUTINE F04AMF (A, LDA, X, LDX, B, LDB, M, N, IR, EPS, QR, LDQR,
ALPHA, E, Y, Z, R, IPIV, IFAIL)
INTEGER
REAL (KIND=nag_wp) A(LDA,N), X(LDX,IR), B(LDB,IR), EPS, QR(LDQR,N),
ALPHA(N), E(N), Y(N), Z(N), R(M)
```

3 Description

To compute the least squares solution to a set of m linear equations in n unknowns $(m \ge n) AX = B$, F04AMF first computes a QR factorization of A with column pivoting, AP = QR, where R is upper triangular, Q is an m by m orthogonal matrix, and P is a permutation matrix. Q^{T} is applied to the m by r right-hand side matrix B to give $C = Q^{T}B$, and the n by r solution matrix X is calculated, to a first approximation, by back-substitution in RX = C. The residual matrix S = B - AX is calculated using *additional precision*, and a correction D to X is computed as the least squares solution to AD = S. X is replaced by X + D and this iterative refinement of the solution is repeated until full machine accuracy has been obtained.

4 References

Wilkinson J H and Reinsch C (1971) Handbook for Automatic Computation II, Linear Algebra Springer-Verlag

5 Parameters

1: A(LDA, N) - REAL (KIND=nag_wp) array

On entry: the m by n matrix A.

2: LDA – INTEGER

On entry: the first dimension of the array A as declared in the (sub)program from which F04AMF is called.

Constraint: $LDA \ge M$.

3: $X(LDX, IR) - REAL (KIND=nag_wp)$ array *Output On exit*: the *n* by *r* solution matrix *X*.

Input

Input

4:	LDX – INTEGER	Input
	<i>On entry</i> : the first dimension of the array X as declared in the (sub)program from which F04AMF is called.	
	<i>Constraint</i> : $LDX \ge N$.	
5:	B(LDB, IR) - REAL (KIND=nag_wp) array	Input
	On entry: the m by r right-hand side matrix B .	
6:	LDB – INTEGER	Input
	<i>On entry</i> : the first dimension of the array B as declared in the (sub)program from which F04AMF is called.	
	Constraint: $LDB \ge M$.	
7:	M – INTEGER	Input
	On entry: m, the number of rows of the matrix A, i.e., the number of equations. Constraint: $M \ge 1$.	
8:	N – INTEGER	Input
	On entry: n, the number of columns of the matrix A, i.e., the number of unknown Constraint: $0 \le N \le M$.	nowns.
9:	IR – INTEGER	Input
	On entry: r, the number of right-hand sides.	
10:	EPS – REAL (KIND=nag_wp)	Input
	On entry: must be set to the value of the machine precision.	
11:	$QR(LDQR, N) - REAL (KIND=nag_wp) array$	Output
	On exit: details of the QR factorization.	
12:	LDQR – INTEGER	Input
	On entry: the first dimension of the array QR as declared in the (sub)pro F04AMF is called.	gram from which
	Constraint: $LDQR \ge M$.	
13:	$ALPHA(N) - REAL (KIND=nag_wp) array$	Output
	On exit: the diagonal elements of the upper triangular matrix R .	
14:	$E(N) - REAL (KIND=nag_wp) array$	Workspace
15:	$Y(N) - REAL (KIND=nag_wp) array$	Workspace
16:	$Z(N) - REAL (KIND=nag_wp) array$	Workspace
17:	R(M) – REAL (KIND=nag_wp) array	Workspace
18:	IPIV(N) – INTEGER array	Output
	On exit: details of the column interchanges.	

Input/Output

On entry: IFAIL must be set to 0, -1 or 1. If you are unfamiliar with this parameter you should refer to Section 3.3 in the Essential Introduction for details.

For environments where it might be inappropriate to halt program execution when an error is detected, the value -1 or 1 is recommended. If the output of error messages is undesirable, then the value 1 is recommended. Otherwise, if you are not familiar with this parameter, the recommended value is 0. When the value -1 or 1 is used it is essential to test the value of IFAIL on exit.

On exit: IFAIL = 0 unless the routine detects an error or a warning has been flagged (see Section 6).

6 Error Indicators and Warnings

If on entry IFAIL = 0 or -1, explanatory error messages are output on the current error message unit (as defined by X04AAF).

Errors or warnings detected by the routine:

IFAIL = 1

The rank of A is less than n; the problem does not have a unique solution.

IFAIL = 2

The iterative refinement fails to converge, i.e., the matrix A is too ill-conditioned.

IFAIL = -99

An unexpected error has been triggered by this routine. Please contact NAG.

See Section 3.8 in the Essential Introduction for further information.

IFAIL = -399

Your licence key may have expired or may not have been installed correctly.

See Section 3.7 in the Essential Introduction for further information.

IFAIL = -999

Dynamic memory allocation failed.

See Section 3.6 in the Essential Introduction for further information.

7 Accuracy

Although the correction process is continued until the solution has converged to full machine accuracy, all the figures in the final solution may not be correct since the correction D to X is itself the solution to a linear least squares problem. For a detailed error analysis see page 116 of Wilkinson and Reinsch (1971).

8 Parallelism and Performance

F04AMF is not threaded by NAG in any implementation.

F04AMF makes calls to BLAS and/or LAPACK routines, which may be threaded within the vendor library used by this implementation. Consult the documentation for the vendor library for further information.

Please consult the X06 Chapter Introduction for information on how to control and interrogate the OpenMP environment used within this routine. Please also consult the Users' Note for your implementation for any additional implementation-specific information.

9 Further Comments

The time taken by F04AMF is approximately proportional to $n^2(3m - n)$, provided r is small compared with n.

10 Example

This example calculates the accurate least squares solution of the equations

```
\begin{array}{l} 1.1x_1 + 0.9x_2 = 2.2\\ 1.2x_1 + 1.0x_2 = 2.3\\ 1.0x_1 + 1.0x_2 = 2.1 \end{array}
```

10.1 Program Text

Program f04amfe

```
!
     F04AMF Example Program Text
     Mark 25 Release. NAG Copyright 2014.
1
      .. Use Statements ..
1
     Use nag_library, Only: f04amf, nag_wp, x02ajf
      .. Implicit None Statement ..
1
     Implicit None
!
      .. Parameters ..
                                       :: nin = 5, nout = 6
     Integer, Parameter
     .. Local Scalars ..
1
     Real (Kind=nag_wp)
                                        :: eps
     Integer
                                        :: i, ifail, ir, lda, ldb, ldqr, ldx,
                                                                                 &
                                          m, n
1
      .. Local Arrays ..
     Real (Kind=nag_wp), Allocatable :: a(:,:), alpha(:), b(:,:), e(:),
                                                                                 &
                                          qr(:,:), r(:), x(:,:), y(:), z(:)
     Integer, Allocatable
                                        :: ipiv(:)
     .. Executable Statements ..
!
     Write (nout,*) 'FO4AMF Example Program Results'
     Write (nout,*)
!
     Skip heading in data file
     Read (nin,*)
     Read (nin,*) m, n
      ir = 1
     lda = m
     ldb = m
      ldgr = m
      ldx = n
     Allocate (a(lda,n),alpha(n),b(ldb,ir),e(n),gr(ldgr,n),r(m),x(ldx,ir), &
       y(n), z(n), ipiv(n))
     Read (nin,*)(a(i,1:n),b(i,1:ir),i=1,m)
      eps = x02ajf()
1
     ifail: behaviour on error exit
              =0 for hard exit, =1 for quiet-soft, =-1 for noisy-soft
1
      ifail = 0
      Call f04amf(a,lda,x,ldx,b,ldb,m,n,ir,eps,qr,ldqr,alpha,e,y,z,r,ipiv, &
        ifail)
     Write (nout,*) ' Solution'
      Do i = 1, n
       Write (nout,99999) x(i,1:ir)
     End Do
99999 Format (1X,8F9.4)
   End Program f04amfe
```

10.2 Program Data

F04AMF Example Program Data 3 2 : m, n 1.1 0.9 2.2 1.2 1.0 2.3 1.0 1.0 2.1 : matrices A and B

10.3 Program Results

F04AMF Example Program Results

Solution 1.3010 0.7935