

# NAG Library Function Document

## nag\_ip\_read (h02xyc)

### 1 Purpose

nag\_ip\_read (h02xyc) reads a set of optional parameter values from a file and assigns those values to a given options structure of type Nag\_H02\_Opt. Values supplied are checked as being of correct type and within range for the specified optional parameter.

### 2 Specification

```
#include <nag.h>
#include <nagh.h>

void nag_ip_read (const char *name, const char *opt_file,
                 Nag_H02_Opt *options, Nag_Boolean print, const char *outfile,
                 NagError *fail)
```

### 3 Description

The integer programming (IP) functions of the h Chapter Introduction have a number of optional parameters, which are set by means of a structure of type Nag\_H02\_Opt. Optional parameter values may be assigned to members of the options structure directly in the program text and/or by supplying the optional values in a file which can be read by the function nag\_ip\_read (h02xyc).

When optional parameter values are read from a file using nag\_ip\_read (h02xyc) then the options structure will be initialized automatically if this has not already been done. It is only necessary to call nag\_ip\_init (h02xxc) if direct assignments to the options structure are made in your program before calling nag\_ip\_read (h02xyc).

As well as reading from a file, nag\_ip\_read (h02xyc) will also read from `stdin`. This allows redirection to be used to supply the file; it also permits nag\_ip\_read (h02xyc) to be used interactively with you supplying values from the keyboard.

Checks are made that the values read in are of valid type for the optional parameter specified and that the value is within the valid range for that argument. If a value is accepted, a printed confirmation of the setting of the relevant argument will be output if `print = Nag_TRUE`. An unacceptable argument name or value will give an error message if `print = Nag_TRUE`.

### 4 References

None.

### 5 Arguments

- 1: **name** – const char \* *Input*  
*On entry:* a character string specifying either the NAG six character name or the NAG long name of the proposed IP function. The case of the character string is disregarded.
- 2: **opt\_file** – const char \* *Input*  
*On entry:* the name of the file which specifies the optional parameter values. If `stdin` is to be used, the string "`stdin`" should be supplied. The set of option values must be preceded by the keyword `begin` followed by the function name for which the set of options is being supplied. The function name may be the six character NAG name of an IP function or its associated long name.

Each option value specified in the file must be preceded by the name of the optional parameter. The argument name and value must be separated by at least one blank space or an equals symbol. `nag_ip_read` (h02xyc) will read to the end of file or until the keyword `end` is found or until another `begin` is found. C style comments may be placed within a set of option values to aid your documentation. Outside the option value sets, text need not be within C style comment delimiters.

N.B. Assignment to function pointers in the options structure, memory allocation to array pointers and assignment of trailing array dimensions cannot be performed from an options file. These must be assigned directly to the options structure in your calling program.

- 3: **options** – Nag\_H02\_Opt \* *Input/Output*  
*On entry:* the options structure may or may not have previously been initialized, and had values assigned to its members.  
*On exit:* the options structure, initialized and with values assigned according to the values found in the options file.
- 4: **print** – Nag\_Boolean *Input*  
*On entry:* if Nag\_TRUE a message confirming the setting of each option will be output.
- 5: **outfile** – const char \* *Input*  
*On entry:* a character string specifying the name of the file to which confirmation messages should be output. If `stdout` is required then the string "stdout" should be given. When **print** = Nag\_FALSE the empty string "" can be supplied as **outfile** will be ignored.
- 6: **fail** – NagError \* *Input/Output*  
The NAG error argument (see Section 2.7 in How to Use the NAG Library and its Documentation).

## 6 Error Indicators and Warnings

### NE\_FIELD\_UNKNOWN

(line *<value>*) '*<string>*' is not a permitted structure member or option for *<string>*.

### NE\_INVALID\_BEGIN

The Begin statement occurring in data file from which options are being read is not valid.

### NE\_INVALID\_ENUM\_RANGE

Enum value *<string>* given to *<option>* is not valid for this function.

### NE\_INVALID\_INT\_RANGE\_1

### NE\_INVALID\_OPTION

(line *<value>*) '*<string>*' cannot be assigned to using an options file.

### NE\_INVALID\_OPTION\_NAME

(line *<value>*) '*<string>*' is not a valid name for a structure member or option.

This error message is output if, for example, the specified string contains characters which are not permitted in a variable name in the C programming language.

**NE\_INVALID\_REAL\_RANGE\_CONS**

Value  $\langle value \rangle$  given to  $\langle option \rangle$  is not valid. The argument  $\langle option \rangle$  must satisfy  $\langle constraint \rangle$ .

**NE\_INVALID\_REAL\_RANGE\_F**

Value  $\langle value \rangle$  given to  $\langle option \rangle$  is not valid. Correct range is  $\langle option \rangle \langle value \rangle$ .

**NE\_INVALID\_REAL\_RANGE\_FF**

Value  $\langle value \rangle$  given to  $\langle option \rangle$  is not valid. Correct range is  $\langle value \rangle \langle option \rangle \langle value \rangle$ .

**NE\_INVALID\_TEXT\_RANGE**

Value  $\langle string \rangle$  given to  $\langle option \rangle$  not valid.

**NE\_INVALID\_VALUE**

(line  $\langle value \rangle$ ) value ‘ $\langle string \rangle$ ’ given to  $\langle string \rangle$  option is not of the correct type for this option.

**NE\_NO\_VALUE**

(line  $\langle value \rangle$ ) no value found for option  $\langle string \rangle$ .

**NE\_NOT\_APPEND\_FILE**

Cannot open file  $\langle string \rangle$  for appending.

**NE\_NOT\_CLOSE\_FILE**

Cannot close file  $\langle string \rangle$ .

**NE\_NOT\_FUN\_NAME**

The string,  $\langle string \rangle$ , supplied in the argument name is not the name of any C Library function with option setting facilities.

**NE\_NOT\_READ\_FILE**

Cannot open file  $\langle string \rangle$  for reading.

**NE\_UNBALANCED\_COMMENT**

Unbalanced comment starting on line  $\langle value \rangle$  found in options file.

**NE\_WRITE\_ERROR**

Error occurred when writing to file  $\langle string \rangle$ .

**7 Accuracy**

Not applicable.

**8 Parallelism and Performance**

nag\_ip\_read (h02xyc) is not threaded in any implementation.

**9 Further Comments**

nag\_ip\_read (h02xyc) may be used to read the optional ‘MPSX names’ (e.g., **prob\_name**, **obj\_name**) for nag\_ip\_mps\_read (h02buc). However, although this function allows the names to contain non-leading blank characters, nag\_ip\_read (h02xyc) will not read such names correctly from an options file since blank spaces are assumed to denote the end of an option name or value within the file. All other

valid MPSX names (see the documentation for nag\_ip\_mps\_read (h02buc) for details) will be read correctly by nag\_ip\_read (h02xyc).

## **10 Example**

See Section 10 in nag\_ip\_mps\_read (h02buc).

---